
Adafruit RTTTL Library Documentation

Release 1.0

Scott Shawcroft

Apr 03, 2018

Contents

| | | |
|----------|--------------------------------|-----------|
| 1 | Dependencies | 3 |
| 2 | Usage Example | 5 |
| 3 | Contributing | 7 |
| 4 | Building locally | 9 |
| 4.1 | Sphinx documentation | 9 |
| 5 | Table of Contents | 11 |
| 5.1 | Simple test | 11 |
| 5.2 | adafruit_rtttl | 12 |
| 6 | Indices and tables | 13 |
| | Python Module Index | 15 |

This plays [RTTTL](#) melodies.

CHAPTER 1

Dependencies

This driver depends on:

- [Adafruit CircuitPython](#)
- [Adafruit CircuitPython Waveform](#)

Please ensure all dependencies are available on the CircuitPython filesystem. This is easily achieved by downloading the [Adafruit library and driver bundle](#).

CHAPTER 2

Usage Example

This plays Frosty the Snowman:

```
import board
import adafruit_rtttl

adafruit_rtttl.play(board.A0, "Snowman:d=8,o=5,b=200:2g,4e.,f,4g,2c6,b,c6,4d6,4c6,4b,
↪a,2g.,b,c6,4d6,4c6,4b,a,a,g,4c6,4e.,g,a,4g,4f,4e,4d,2c.,4c,4a,4a,4c6,4c6,4b,4a,4g,
↪4e,4f,4a,4g,4f,2e.,4e,4d,4d,4g,4g,4b,4b,4d6,d6,b,4d6,4c6,4b,4a,4g,4p,2g")
```


CHAPTER 3

Contributing

Contributions are welcome! Please read our [Code of Conduct](#) before contributing to help this project stay welcoming.

CHAPTER 4

Building locally

To build this library locally you'll need to install the `circuitpython-build-tools` package.

```
python3 -m venv .env
source .env/bin/activate
pip install circuitpython-build-tools
```

Once installed, make sure you are in the virtual environment:

```
source .env/bin/activate
```

Then run the build:

```
circuitpython-build-bundles --filename_prefix adafruit-circuitpython-rtttl --library_
↳location .
```

4.1 Sphinx documentation

Sphinx is used to build the documentation based on rST files and comments in the code. First, install dependencies (feel free to reuse the virtual environment from above):

```
python3 -m venv .env
source .env/bin/activate
pip install Sphinx sphinx-rtd-theme
```

Now, once you have the virtual environment activated:

```
cd docs
sphinx-build -E -W -b html . _build/html
```

This will output the documentation to `docs/_build/html`. Open the `index.html` in your browser to view them. It will also (due to `-W`) error out on any warning like Travis will. This is a good way to locally verify it will pass.

5.1 Simple test

Ensure your device works with this simple test.

Listing 5.1: examples/rtttl_simpletest.py

```
1 # The MIT License (MIT)
2 #
3 # Copyright (c) 2017 Scott Shawcroft for Adafruit Industries
4 #
5 # Permission is hereby granted, free of charge, to any person obtaining a copy
6 # of this software and associated documentation files (the "Software"), to deal
7 # in the Software without restriction, including without limitation the rights
8 # to use, copy, modify, merge, publish, distribute, sublicense, and/or sell
9 # copies of the Software, and to permit persons to whom the Software is
10 # furnished to do so, subject to the following conditions:
11 #
12 # The above copyright notice and this permission notice shall be included in
13 # all copies or substantial portions of the Software.
14 #
15 # THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR
16 # IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY,
17 # FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE
18 # AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER
19 # LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
20 # OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN
21 # THE SOFTWARE.
22
23 # This is tested on the CircuitPlayground Express
24
25 import adafruit_rtttl
26 import digitalio
27 import board
28
```

```
29 enable = digitalio.DigitalInOut(board.SPEAKER_ENABLE)
30 enable.switch_to_output(value=True)
31
32 adafruit_rtttl.play(board.SPEAKER, "itchy:d=8,o=6,b=160:c,a5,4p,c,a,4p,c,a5,c,a5," + \
33     "c,a,4p,p,c,d,e,p,e,f,g,4p,d,c,4d,f,4a#,4a,2c7")
34 adafruit_rtttl.play(board.SPEAKER, "Phantom:d=4,o=5,b=140:c,f,c,d#. ,8c#,2c#,a#4," + \
35     "d#,8a#4,2c,c,f,c,d#. ,8c#,2c#,a#4,d#. ,8a#4,2c,p,c,f,g#,c.6,8a#,2a#,a#,d#.6,8a#,"
↪+ \
36     "2c6,p,c6,2f.6,8d#6,8c#6,8c6,8a#,8g#,8g,8f,2e,c#,c#. ,8c,2c")
```

5.2 adafruit_rtttl

Play notes to a digitalio pin using ring tone text transfer language (rtttl).

- Author(s): Scott Shawcroft

`adafruit_rtttl.play` (*pin*, *rtttl*, *octave=None*, *duration=None*, *tempo=None*)

Play notes to a digitalio pin using ring tone text transfer language (rtttl). :param ~digitalio.DigitalInOut pin: the speaker pin :param rtttl: string containing rtttl :param int octave: represents octave number (default 6 starts at middle c) :param int duration: length of notes (default 4 quarter note) :param int tempo: how fast (default 63 beats per minute)

CHAPTER 6

Indices and tables

- `genindex`
- `modindex`
- `search`

a

`adafruit_rtttl`, 12

A

[adafruit_rtttl \(module\)](#), [12](#)

P

[play\(\)](#) (in module [adafruit_rtttl](#)), [12](#)