
Adafruit NeoPixel Library Documentation

Release 1.0

**Scott Shawcroft
Damien P. George**

May 03, 2018

Contents

1	Dependencies	3
2	Usage Example	5
3	Contributing	7
4	Building locally	9
4.1	Sphinx documentation	9
5	Table of Contents	11
5.1	Simple test	11
5.2	neopixel - NeoPixel strip driver	12
6	Indices and tables	15
	Python Module Index	17

Higher level NeoPixel driver that presents the strip as a sequence. This is a supercharged version of the original MicroPython driver. Its now more like a normal Python sequence and features slice support, `repr` and `len` support.

Colors are stored as tuples by default. However, you can also use int hex syntax to set values similar to colors on the web. For example, `0x100000` (`#100000` on the web) is equivalent to `(0x10, 0, 0)`.

Note: The int hex API represents the brightness of the white pixel when present by setting the RGB channels to identical values. For example, full white is `0xffffffff` but is actually `(0, 0, 0, 0xff)` in the tuple syntax. Setting a pixel value with an int will use the white pixel if the RGB channels are identical. For full, independent, control of each color component use the tuple syntax.

CHAPTER 1

Dependencies

This driver depends on:

- [Adafruit CircuitPython](#)

Please ensure all dependencies are available on the CircuitPython filesystem. This is easily achieved by downloading the [Adafruit library and driver bundle](#).

CHAPTER 2

Usage Example

This example demonstrates the library with the single built-in NeoPixel on the [Feather M0 Express](#) and [Metro M0 Express](#).

```
import board
import neopixel

pixels = neopixel.NeoPixel(board.NEOPIXEL, 1)
pixels[0] = (10, 0, 0)
```

This example demonstrates the library with the ten built-in NeoPixels on the [Circuit Playground Express](#). It turns off `auto_write` so that all pixels are updated at once when the `show` method is called.

```
import board
import neopixel

pixels = neopixel.NeoPixel(board.NEOPIXEL, 10, auto_write=False)
pixels[0] = (10, 0, 0)
pixels[9] = (0, 10, 0)
pixels.show()
```

This example demonstrates using a single NeoPixel tied to a GPIO pin and with a `pixel_order` to specify the color channel order. Note that `bpp` does not need to be specified as it is computed from the supplied `pixel_order`.

```
import board
import neopixel

pixel = neopixel.NeoPixel(board.D0, 1, pixel_order=neopixel.RGBW)
pixel[0] = (30, 0, 20, 10)
```


CHAPTER 3

Contributing

Contributions are welcome! Please read our [Code of Conduct](#) before contributing to help this project stay welcoming.

CHAPTER 4

Building locally

To build this library locally you'll need to install the `circuitpython-build-tools` package.

```
python3 -m venv .env
source .env/bin/activate
pip install circuitpython-build-tools
```

Once installed, make sure you are in the virtual environment:

```
source .env/bin/activate
```

Then run the build:

```
circuitpython-build-bundles --filename_prefix adafruit-circuitpython-neopixel --
↳library_location .
```

4.1 Sphinx documentation

Sphinx is used to build the documentation based on rST files and comments in the code. First, install dependencies (feel free to reuse the virtual environment from above):

```
python3 -m venv .env
source .env/bin/activate
pip install Sphinx sphinx-rtd-theme
```

Now, once you have the virtual environment activated:

```
cd docs
sphinx-build -E -W -b html . _build/html
```

This will output the documentation to `docs/_build/html`. Open the `index.html` in your browser to view them. It will also (due to `-W`) error out on any warning like Travis will. This is a good way to locally verify it will pass.

5.1 Simple test

Ensure your device works with this simple test.

Listing 1: examples/neopixel_simpletest.py

```
1  # CircuitPython demo - NeoPixel
2
3  import time
4  import board
5  import neopixel
6
7
8  # On CircuitPlayground Express -> Board.NEOPIXEL
9  # Otherwise choose an open pin connected to the Data In of the NeoPixel strip,
10 # such as board.D1
11 pixpin = board.NEOPIXEL
12
13 # The number of pixels in the strip
14 numpix = 10
15
16 # number of colors in each pixel, =3 for RGB, =4 for RGB plus white
17 BPP = 3
18
19 strip = neopixel.NeoPixel(pixpin, numpix, bpp=BPP, brightness=0.3, auto_write=False)
20
21 def format_tuple(r, g, b):
22     if BPP == 3:
23         return (r, g, b)
24     return (r, g, b, 0)
25
26 def wheel(pos):
27     # Input a value 0 to 255 to get a color value.
```

(continues on next page)

(continued from previous page)

```

28     # The colours are a transition r - g - b - back to r.
29     if (pos < 0) or (pos > 255):
30         return format_tuple(0, 0, 0)
31     if pos < 85:
32         return format_tuple(int(pos * 3), int(255 - (pos*3)), 0)
33     elif pos < 170:
34         pos -= 85
35         return format_tuple(int(255 - pos*3), 0, int(pos*3))
36     #else:
37     pos -= 170
38     return format_tuple(0, int(pos*3), int(255 - pos*3))
39
40 def rainbow_cycle(wait):
41     for j in range(255):
42         for i in range(strip.n):
43             idx = int((i * 256 / len(strip)) + j)
44             strip[i] = wheel(idx & 255)
45             strip.show()
46             time.sleep(wait)
47
48 while True:
49     strip.fill(format_tuple(255, 0, 0))
50     strip.show()
51     time.sleep(1)
52
53     strip.fill(format_tuple(0, 255, 0))
54     strip.show()
55     time.sleep(1)
56
57     strip.fill(format_tuple(0, 0, 255))
58     strip.show()
59     time.sleep(1)
60
61     rainbow_cycle(0.001)    # rainbowcycle with 1ms delay per step

```

5.2 neopixel - NeoPixel strip driver

- Author(s): Damien P. George & Scott Shawcroft

`neopixel.GRB = (1, 0, 2)`
Green Red Blue

`neopixel.GRBW = (1, 0, 2, 3)`
Green Red Blue White

class `neopixel.NeoPixel` (*pin, n, *, bpp=3, brightness=1.0, auto_write=True, pixel_order=None*)
A sequence of neopixels.

Parameters

- **pin** (*Pin*) – The pin to output neopixel data on.
- **n** (*int*) – The number of neopixels in the chain
- **bpp** (*int*) – Bytes per pixel. 3 for RGB and 4 for RGBW pixels.

- **brightness** (*float*) – Brightness of the pixels between 0.0 and 1.0 where 1.0 is full brightness
- **auto_write** (*bool*) – True if the neopixels should immediately change when set. If False, *show* must be called explicitly.
- **pixel_order** (*tuple*) – Set the pixel color channel order. GRBW is set by default.

Example for Circuit Playground Express:

```
import neopixel
from board import *

RED = 0x100000 # (0x10, 0, 0) also works

pixels = neopixel.NeoPixel(NEOPIXEL, 10)
for i in range(len(pixels)):
    pixels[i] = RED
```

Example for Circuit Playground Express setting every other pixel red using a slice:

```
import neopixel
from board import *
import time

RED = 0x100000 # (0x10, 0, 0) also works

# Using ``with`` ensures pixels are cleared after we're done.
with neopixel.NeoPixel(NEOPIXEL, 10) as pixels:
    pixels[::2] = [RED] * (len(pixels) // 2)
    time.sleep(2)
```

brightness

Overall brightness of the pixel

deinit()

Blank out the NeoPixels and release the pin.

fill (*color*)

Colors all pixels the given **color**.

show()

Shows the new colors on the pixels themselves if they haven't already been autowritten.

The colors may or may not be showing after this function returns because it may be done asynchronously.

write()

Use show instead. It matches Micro:Bit and Arduino APIs.

```
neopixel.RGB = (0, 1, 2)
```

Red Green Blue

```
neopixel.RGBW = (0, 1, 2, 3)
```

Red Green Blue White

CHAPTER 6

Indices and tables

- `genindex`
- `modindex`
- `search`

n

neopixel, [12](#)

B

brightness (neopixel.NeoPixel attribute), [13](#)

D

deinit() (neopixel.NeoPixel method), [13](#)

F

fill() (neopixel.NeoPixel method), [13](#)

G

GRB (in module neopixel), [12](#)

GRBW (in module neopixel), [12](#)

N

NeoPixel (class in neopixel), [12](#)

neopixel (module), [12](#)

R

RGB (in module neopixel), [13](#)

RGBW (in module neopixel), [13](#)

S

show() (neopixel.NeoPixel method), [13](#)

W

write() (neopixel.NeoPixel method), [13](#)